2013

2 Save Energy Limited

[NETWORK OWL MULTICAST PROTOCOL]

Description of the XML data packets sent by the Network OWL via multicast UDP, multicast settings and links to example source code. For use with Network OWL firmware v2.0

CONTENTS

Change History	. 2
ntroduction	2
Multicast Configuration	2
Settings	2
Multicast Packets	2
Electricity Data Packet	2
Example Packet	2
Parameters	3
Solar Data Packet	3
Example Packet	3
Parameters	3
Weather Data Packet	4
Example Packet	4
Parameters	4
Weather Codes	4
Heating Data Packet	5
Example Packet	5
Parameters	5

CHANGE HISTORY

Date	Author	Description
25/01/2013	BW	Initial draft containing example packets

INTRODUCTION

MULTICAST CONFIGURATION

SETTINGS

The Network OWL sends UDP packets to the following multicast group:

Address: 224.192.32.19

Port: 22600

There are a number of multicast examples available on the internet, some listed below. The values above can be used with these examples to get you started receiving multicast data from the Network OWL.

Java

http://lycog.com/programming/multicast-programming-java/

C/C++

http://ntrg.cs.tcd.ie/undergrad/4ba2/multicast/antony/example.html

MULTICAST PACKETS

ELECTRICITY DATA PACKET

EXAMPLE PACKET

```
<electricity id='443719999999'>
    <signal rssi='-71' lqi='127'/>
    <battery level='100%'/>
    <chan id='0'><curr units='w'>483.00</curr><day units='wh'>10244.99</day></chan>
    <chan id='1'><curr units='w'>0.00</curr><day units='wh'>0.00</day></chan>
    <chan id='2'><curr units='w'>0.00</curr><day units='wh'>0.00</day></chan>
</electricity>
```

PARAMETERS

The <chan> tags contain data for the current reading (<curr>) and the daily total (<day>) for each of the channels/phases on the electricity transmitter. If the transmitter only has 1 channel, the last 2 channels will always contain 0 values.

Tag	Attribute	Description
Electricity	Id	The MAC Address of the Network OWL
Signal	rssi	Receive signal strength (dBm)
Signal	lqi	Link quality (closer to 0 the better)
Battery	level	Percentage of battery remaining
Chan	id	Transmitter channel number
Curr/Day	units	Units for the value in the xml tag.
		wh = Watt Hours, divide by 1000 to get kWh
		w = watts

SOLAR DATA PACKET

EXAMPLE PACKET

<solar id='00A0C914C851'>

<current><generating units='w'>0.00</generating><exporting units='w'>0.00</exporting></current>
 <day><generated units='wh'>0.00</generated><exported units='wh'>0.00</exported></day>
 </solar>

PARAMETERS

The main <solar> tag contains sections for the current solar readings (<current>) and the totals for the day (<day>). Both sections have <generated> and <exported> tags that contain the values for power generated by the PV system and power exported to the electricity grid.

Tag	Attribute	Description
Solar	Id	The MAC Address of the Network OWL
Curr/Day	units	Units for the value in the xml tag. wh = Watt Hours, divide by 1000 to get kWh w = watts

WEATHER DATA PACKET

EXAMPLE PACKET

<weather id='00A0C914C851' code='263'>
 <temperature>19.00</temperature>
 <text>Patchy light drizzle</text>
</weather>

PARAMETERS

The <weather> tag contains temperature and text subsections. The <temperature> is the current outside temperature for the postcode assigned to the Network OWL. The text is a textural description of the weather at that postcode.

Tag	Attribute	Description
Weather	id	The MAC Address of the Network OWL
Weather	code	Weather condition code (see below)

WEATHER CODES

Code	Description		
113	Clear/Sunny		
116	Partly Cloudy		
119	Cloudy		
122	Overcast		
143	Mist		
176	Patchy rain nearby		
179	Patchy snow nearby		
182	Patchy sleet nearby		
185	Patchy freezing drizzle nearby		
200	Thundery outbreaks		
227	Blowing snow		
230	Blizzard		
248	Fog		
260	Freezing fog		
263	Patchy light drizzle		
266	Light drizzle		
281	Freezing drizzle		
284	Heavy freezing drizzle		
293	Patchy light rain		
296	Light rain		
299	Moderate rain at times		
302	Moderate rain		
305	Heavy rain at times		
308	Heavy rain		
311	Light freezing rain		
314	Moderate or Heavy freezing rain		
317	Light sleet		
320	Moderate or heavy sleet		
323	Patchy light snow		

326	Light snow		
329	Patchy moderate snow		
332	Moderate snow		
335	Patchy heavy snow		
338	Heavy snow		
350	Ice pellets		
353	Light rain shower		
356	Moderate or heavy rain shower		
359	Torrential rain shower		
362	Light sleet showers		
365	Moderate or heavy sleet showers		
368	Light snow showers		
371	Moderate or heavy snow showers		
374	Light showers of ice pellets		
377	Moderate or heavy showers of ice pellets		
386	Patchy light rain in area with thunder		
389	Moderate or heavy rain in area with thunder		
392	Patchy light snow in area with thunder		
395	Moderate or heavy snow in area with thunder		

HEATING DATA PACKET

EXAMPLE PACKET

```
<heating id='00A0C914C851'>
  <signal rssi='-61' |qi='48'/>
  <battery level='2730mV'/>
  <temperature until='1359183600' zone='0'>
        <current>22.37</current>
        <required>15.00</required>
        </temperature>
  </heating>
```

PARAMETERS

The <heating> tag contains a temperature subsection, which contains the current room temperature (<current>) and the required room temperature (<required>). Both values are in degrees Celsius.

Tag	Attribute	Description
Heating	Id	The MAC Address of the Network OWL
Signal	rssi	Receive signal strength (dBm)
Signal	lqi	Link quality (closer to 0 the better)
Battery	level	Battery voltage reading in millivolts
Temperature	until	Timestamp of the end of the current comfort/standby period
Temperature	Zone	Current active heating zone